

Table of Content

1.	Introduction	3
2.	GENIUS VOIP MOUSE Installation and Un-installation	4
2.1	System requirement	4
2.2	IMs supported by GENIUS VOIP MOUSE	5
2.3	IMs not supported by GENIUS VOIP MOUSE at present	5
2.4	Website of each IM to download	5
2.5	GENIUS VOIP MOUSE software installation	6
2.6	GENIUS VOIP MOUSE software un-installation	8
3.	Description of GENIUS VOIP MOUSE GUI	9
4.	Accounting Management	10
4.1	Run the IMs automatically by GENIUS VOIP MOUSE	10
4.2	Run the IMs with pre-setting Auto Login by GENIUS VOIP MOUSE	10
4.3	Run the IMs with pre-setting Auto Run by GENIUS VOIP MOUSE	11
4.4	Run the IMs without pre-setting Auto Run, Auto Login by GENIUS VOIP MOUSE	11
4.5	How to add/delete/edit your IM accounts in GENIUS VOIP MOUSE	12
4.6	How to setup automatic login account for each IM in GENIUS VOIP MOUSE	13
4.7	How to run the IM automatically in GENIUS VOIP MOUSE	13
5.	IM account status management	14
5.1	Status Synchronization between IM status and GENIUS VOIP MOUSE	14
5.2	Definition on the status of the IM icons	15
6.	Dialing function	16
6.1	Input +, *, # and 0~9	16
6.2	Remove button	16
6.3	Quick search for national region code	17
7.	Contact list	18
7.1	Find the contact list according to the IM	19
7.2	Sorting the contact list by IM/Name in ascending/ descending	19
7.3	Show all the contacts or those online contacts only	19
7.4	Look at the information about the IM contact	20
7.5	Add a new IM friend	20

7.6 Search for a friend in the specific IM	21
7.7 Quick Search for a friend in contact list	22
7.8 Make an IM call	22
7.9 Chat with your friend	23
7.10 Send files to your friend	24
8. Active Call Function	25
9. Phone Book	26
9.1 Add a new friend to the phone book	27
9.2 Import contact friends to the phone book	27
9.3 Quick Search for a friend in phone book	28
9.4 Communication with contact in phone book function dialog	29
10. Call History	30
10.1 Description on the icons in call history	30
10.2 Make a call in call history dialog	30
11. Call Alert	31
12. Online Update	31

1. Introduction

Thank you for choosing this new Genius mouse device with the new software called GENIUS VOIP MOUSE for main-stream Instant messenger programs (IMs). This software works with the six most popular IMs -- Skype, Google Talk, MSN Messenger, AOL, Yahoo Messenger and QQ.

This universal interface can control the six main-stream IMs in a simple and convenient way to chat, send files, message to/with your friends. You can easily manage the different IM's contact list in one dialog box with quick sorting, search, call history and editing support.


This GENIUS VOIP MOUSE software manual is a guide so you know how to (a) install or remove the GENIUS VOIP MOUSE step by step, (b) the OS system requirement and (c) the information of abnormal messages. We are confident that GENIUS VOIP MOUSE software will make all your instant messaging easy.

2. GENIUS VOIP MOUSE Installation and Un-Installation

2.1 System requirement

We recommend using this device on a USB port. You need to confirm your PC operation system supports USB function, USB 1.1 or 2.0.

- OS Support: WinXP (SP1~SP2), Win2000 (SP1~SP4)
- System recommended: Intel Pentium 4 or AMD K7 CPU above
- At least 128MB RAM (Win2000 and WinXP)
- At least 50 MB hard disk space
- Supported IM version listed in the 「Help」 page of GENIUS VOIP MOUSE
- For good sound quality, please adjust your system's H/W acceleration and Sample rate conversion quality to Full and Best.




*** Important Notice ***

1. Before you install the VOIP software application and driver, you must make sure that the Internet Phone Mouse is already connected to the PC. Otherwise, the GENIUS VOIP MOUSE driver will fail to install during the installation.
2. For the call forward function, make sure that the Home Gate Way device has been connected to a PSTN line and Telephone.
3. When you have completed the installation procedure, the system will keep on-board audio priority and use Skype as the primary Internet Phone Mouse.
4. If your PC system has more than one USB port, please remember which one you used, because the next time when you plug this Internet Phone Mouse to your PC, you have to plug it into the same port to initialize the software driver.

2.2 IMs supported by GENIUS VOIP MOUSE

You can get the supported IM version in the 「Help」 sheet of the GENIUS VOIP MOUSE main dialog UI.



2.4 Websites of Each IM to download

- Skype: <http://www.skype.com/download>
- Google Talk: <http://www.google.com/talk>
- MSN Messenger: <http://messenger.msn.com/download>
- AIM: <http://www.aim.com>
- Yahoo Messenger: <http://messenger.yahoo.com>
- QQ: <http://im.qq.com>

2.5 GENIUS VOIP MOUSE Software Installation


We recommend you remove the previous mouse software before you install the GENIUS VOIP MOUSE software application

The installation steps are as follows:

STEP-1: Plug in Navigator 380 and insert Installation CD on your CD-ROM or DVD ROM, the




program will pop up GENIUS VOIP MOUSE.exe then execute the installation program.




If you did not insert Navigator 380 prior to installing the GENIUS VOIP MOUSE software, this dialog will not show up during the installation procedure. It will go to the end directly.

STEP-2: After you installed the GENIUS VOIP MOUSE and driver programs, a window will pop up and ask you to restart your PC immediately or later. Select what you would like and click 「Finish」 button to complete and launch GENIUS VOIP MOUSE.



STEP-3: There are two methods to start GENIUS VOIP MOUSE. You can double click on the short-cut GENIUS VOIP MOUSE icon on the PC screen or you can execute the AP


software in the OS through "Start Menu"  → All programs Menu



STEP-4: A GENIUS VOIP MOUSE Mail Dialog window will pop up on your PC screen with the status of each IM.




STEP-5: If you did not install all the IMs supported by GENIUS VOIP MOUSE, a window will pop up asking you to download those un-installed IMs and setup auto-run/auto login for the first time.





2.6 GENIUS VOIP MOUSE Software Un-installation

You can remove the GENIUS VOIP MOUSE and its driver from the PC these two ways.

Method-1, remove the GENIUS VOIP MOUSE software through “Start Menu  →




Method-2, remove GENIUS VOIP MOUSE via “Start Menu  → Control Panel



3. Description of the GENIUS VOIP MOUSE GUI

Once again, you must to install Navigator 380 into your PC before you can enjoy the GENIUS VOIP MOUSE software. There are six functional sub-dialogs in the main of the GENIUS VOIP MOUSE. Open the GENIUS VOIP MOUSE. In addition, this guide will describe all the functions in detail.




4.Accounting Management

This section will show you how to run each IM by GENIUS VOIP MOUSE automatically by taking advantage of the accounting management.


4.1 Run the IMs automatically by GENIUS VOIP MOUSE

If you already installed the IMs by auto-run and auto-login in the account management, GENIUS VOIP MOUSE will detect and run those IMs automatically.



4.2 Run the IMs with pre-setting Auto Login by GENIUS VOIP MOUSE

If those IMs have been installed with setting auto-login previously, you can use the Account Management to run these IMs by GENIUS VOIP MOUSE. The setting procedure is as follows.



4.3 Run the IMs with pre-setting Auto-Run by GENIUS VOIP MOUSE

If those IMs have been installed with setting auto-run previously, you can use the Account Management to run these IMs by GENIUS VOIP MOUSE. The setting procedure is as follows.

1. Choose the account that you want to run by Genius VOIP Mouse

2. Click on Edit Account

3. Enable Auto Login and Click on O button, then close Setting dialog.

4.4 Run the IM without pre-setting Auto Run and Auto Login by GENIUS VOIP MOUSE

If those IMs have been installed without setting auto-login and auto-run previously, you can still use Account Management to run these IMs by GENIUS VOIP MOUSE. The setting procedure is as follows:

1. Enable Auto-Run by clicking on it

2. Choose the account that you want to edit

3. Click on Edit Account


4. Enable Auto Logic and Click on OK, then close Setting dialog

4.5 How to add/ delete/ edit your IM accounts in GENIUS VOIP MOUSE


STEP-1: Click on “File” in the main GENIUS VOIP MOUSE GUI to enter the Account Management.

STEP-2: Choose the IM that the account will be added.

STEP-3: Click the New Account icon to pop up the edit IM account window.



STEP-4: Choose the IM account you want to edit. Then, click on the “Edit account” icon in the account management. It will pop up the Edit IM Account window for you to edit it.



STEP-5: Choose the IM account you want to remove. Then, click on the “Remove account” icon in the account management.


4.6 How to setup automatical log-in account for each IM in GENIUS VOIP MOUSE

Each IM just can be assigned one auto-login account in GENIUS VOIP MOUSE.

STEP-1: Choose an account you want to login automatically.

STEP-2: Click on the “Edit Account” icon in account management. It will pop up the window to edit.

STEP-3: Choose Auto-Login and click OK button. You can see this account is to be assigned to be Auto Login in the account management dialog.




4.7 How to run the IM automatically in GENIUS VOIP MOUSE

You run the IM automatically with the GENIUS VOIP MOUSE initiation if you set auto-run the IM with an assigned auto-login account.

STEP-1: Choose an auto-login account of the IM as described in 4.6.

STEP-2: Setup Auto Run in the account management dialog as shown below.









5. IM account status management







5.1 Status Synchronization between IM status and GENIUS VOIP MOUSE

You can change the IM status in all-instant-messenger as shown.



In case there is any change on the contact person in IM, GENIUS VOIP MOUSE will synchronize the status automatically to the IM status icons at the same time.

IM Display Icons	The corresponding IM software
	Skype
	Google Talk
	MSN Messenger
	AOL Instant Messenger (abbreviate as AIM)
	Yahoo Messenger
	QQ

Contact person status display icons	Status of contact person
	On line
	Off line
	N/A
	Invisible
	Do not disturb
	Away






5.2 Definition on the status of the IM Icons

GENIUS VOIP MOUSE can synchronize the status of each IM in real-time. You can watch all the IM status on the bottom of the GENIUS VOIP MOUSE main dialog window.




(IM status Icons in GENIUS VOIP MOUSE)

IM Status Definition:

Icons	Status	Skype	Google Talk	MSN Messenger	AIM	Yahoo Messenger	QQ
Color IM Icons	Online	✓	✓	✓	✓	✓	✓
	Away	✓		✓			
	N/A	✓		✓			
	Do not disturb	✓		✓			
	Invisible	✓		✓			✓
	Off line	✓	✓	✓	✓	✓	✓
Gray IM Icons	Logout	✓	✓	✓	✓	✓	✓

6. Dialing function

Click the buttons to control the dialing dialog interface for **Skype Out**.



6.1 Input +, *, # and 0 ~ 9


Input the phone numbers by clicking on the soft digital buttons on the dialing panel. At the same time, the input numbers will show on the display screen.


6.2 Remove button




1. "←" to remove the previous input digital one by one.
2. "C" to remove all the input digital at a time.

6.3 Quick search for national region code


1. Click  icon on the display screen. It will pop up the region code window.



2. [Method-1]: Choose the Country/Region and Area/City using down arrow 「 ▼ 」
[Method-2]: Or you can type in 「 Country/Region 」 or 「 Area/City 」 . It will search automatically for you.




3. The region code will show on the display screen as below after your click the 「 OK 」 icon...










4. Further, user can call a PSTN phone through Skype out.
5. When users would like to search for a region code again, follow the steps above.

7. Contact list

This user interface support shows all IM contact lists in GENIUS VOIP MOUSE. When the contact person was assigned a quick dialing number, the quick dialing number will show up to the right of the contact person in the list.



Available functions in the contact list. When users move mouse over the icon, a description will pop up.

Function icons in contact list	Description of this icon
	Sort the contact list
	Add a new IM friend
	Chat with IM friend
	Send files to IM friend
	Refresh the contact list
	Search for a IM friend
	Information about the IM contact

7.1 Find the contact list according to the IM

STEP-1: Click on the IM icon.



STEP-2: The contact list will show the contact persons belonging to the assigned IM only.

7.2 Sorting the contact list by IM or Name in ascending or descending

STEP-1: Click on the icon (sorting by Name) or (sorting by IM)

STEP-2: Click the icon, the contact list will be sorted in ascending order by the first character.

STEP-3: Click a second time, and the contact list will be sorted in descending order.

STEP-4: It will switch between descending and ascending order each time you click on the icon.


7.3 Show all the contacts or those online contacts only

If you want to show IM contact persons by specific grouping, follow these steps.

STEP-1: Click on Groups: All Friends

STEP-2: Choose the approach you want. Then, all your IM contacts will show up in the approach you have chosen.


You can choose from (a) All Friends (b) Online Friends (c) Offline Friends (d) Skype-Out Friends




7.4 Look at the information about the IM contact

If you want to look at the contact information in detail, follow these steps.


STEP-1: Choose the contact you want to look at the information

STEP-2: Click on the icon . It will pop up a contact information table.




7.5 Add a new IM friend

Except IM itself, you can add a new IM friend in GENIUS VOIP MOUSE, too.


STEP-1: Click on the add icon. 

STEP-2: A window will pop up to add a new contact friend.




STEP-3: Choose the IM you want to add the new friend and click add button.

STEP-4: It will link to this IM and popup the add/search contact window. (ex: Skype)




7.6 Search for a friend in the specific IM

STEP-1: Click the  icon. The search contacts window will appear.

STEP-2: Choose the IM you want to search and click search button.



STEP-3: It will link to the IM and pop up its search window. (ex: Skype)




7.7 Quick Search for a friend in contact list

If you have many friends in your contact list, you can take advantage of the quick search function by the following steps.

STEP-1: Type in the contact name in the quick search window.

STEP-2: The contact friend list will decrease with the characters you type in.




7.8 Make an IM phone call

You can make an IM phone call various ways.

[Approach-1]

STEP-1: Choose the contact in the contact list. The selected friend will be marked in grey.



STEP-2: Click on call  button to make an IM phone call.

[Approach-2]


STEP-1: Choose the contact in the contact list. The chosen friend will be marked in grey.

STEP-2: Double click on the contact friend in contact list to make the IM phone call.

[Approach-3]

STEP-1: Choose the contact in the contact list. The chosen friend will be marked in grey.

STEP-2: Click the right button on the mouse.



STEP-3: Choose **Call** on the popup window to make the IM phone call.


7.9 Chat with your friends

You can chat with your friend in different ways.

[Approach-1]

STEP-1: Choose the contact in the contact list. The chosen friend will be marked in grey.


STEP-2: Click the right button on the mouse.



STEP-3: Choose **Chat** on the popup window to chat with your friend.

[Approach-2]

STEP-1: Choose the contact in the contact list. The selected friend will be marked in grey.

STEP-2: Click  icon to chat with your friend.


7.10 Send files to your friends

You can send files to your friend by various methods.

[Approach-1]

STEP-1: Choose the contact in the contact list. The chosen friend will be marked in grey.


STEP-2: Click the right button on the mouse.



STEP-3: Choose **Send Files** on the popup window to send files to your friends.


[Approach-2]





STEP-1: Choose the contact in the contact list. The chosen friend will be marked in grey.

STEP-2: Click  icon to send a file to your friend.

8. Active Call Function


The active call interface only shows up while the IM call is on going. This interface will disappear when you hang up the IM call. After that, this call information will be recorded into Call History dialog.








Active Call Icons	Description of this icon
	Answer or make a call
	Hang up
	Hold a IM call
	Recoding the IM call

9. Phone Book

This function lets you manage the contact person information in detail in order to chat, call to and send an e-mail to the friend quickly.



Function Icons in Phone Book	Description of this icon
	Sort the list (same as sort contact list)
	Add a new IM friend to phone book
	Chat with IM friend
	Import contact to phone book
	Send e-mail
	Delete the contact from phone book
	Information about the IM contact

9.1 Add a new friend to the phone book


STEP-1: Click [add] icon. Then, it will pop up the window for you to add a new friend to the phone book.

STEP-2: Edit the information in the dialog box, then click [Add].


9.2 Import contact friends to the phone book

There are three methods to import contact information to the phone book.

STEP-1: Click  to choose which method to import information to phone book.



STEP-2: It will pop up a window to import from IM, Outlook Express and vCAR file.




9.3 Quick Search for a friend in Phone Book

If there are many contact friends in your phone book, you can use the quick search function.

STEP-1: Type in the contact name into quick search.

STEP-2: The whole contact friend list will decrease as you type in the characters.



9.4 Communication with contact in phone book function dialog

All the communication approaches are same as that in contact list. You can refer to sections 7.7~7.10.


In addition, you can send e-mails to friends by the following steps.

STEP-1: Make sure the e-mail address is available in the phone book.

STEP-2: Click  button to send e-mail.

10. Call History

When the IM call ends, this call information will be recorded into the Call History dialog box.



10.1 Description on the icons in Call History


Icons	Description
	Sort the call history
	Show all the call history
	Show missed call history
	Show incoming call history
	Show outgoing call history
	Delete the call information from call history

10.2 Make a Call in call history dialog

If you find any important missed calls in the call history, you can directly click on the contact to make a call.

11. Call Alert

If you do not take any action on the incoming call before your friend hangs up the call, the GENIUS VOIP MOUSE software can support the call alert function and show a warning message for a missed call automatically



The missing call alert will provide the names of the IM contact and how many times you missed the IM call.

If the incoming call is missed over 3 times, the call alert will be listed in red.

12. Online Update

You can go to the Genius website to update the GENIUS VOIP MOUSE software.

<http://www.geniusnet.com>